ISTITUTO DI INGEGNERIA DEL MARE INSTITUTE OF MARINE ENGINEERING

Installazione Client VPN per WINDOWS/LINUX

SERVIZIO SISTEMI INFORMATIVI SEDE CENTRALE ROMA

1) Indirizzare il browser su https:193.206.131.110 Inserire user name e nassword

me Folder 72.16.16.1:44	3 C Q Search ☆ 自 ♥ ↓ 1	• Ø =
SonicWALL VI	rtual Office	
Welcome to the De Dell SonicWALL Virtual Office pro	Il SonicWALL Virtual Office ides secure Internet access for remote users to log in	
and access private network reso	rces via SSLVPN technology.	
	User Name: Test Password:	
	Domain: cnrinmrm.local	

cliccare su Login



SERVIZIO SISTEMI INFORMATIVI SEDE CENTRALE ROMA

			· • • • •
u Virtual O	ffice	Welcome, Tes	t! Logout
o the Dell Soni	cWALL Virtual Of	fice	
tual Office provides secure	e Internet access for remote u	isers to log in	
red bookmark or create yo resources.	our own to gain secure Intern	et access to	
er to create an SSLVPN tun	nel to your corporate networ	k for full	
ownload Windows Mobile M ownload Linux NetExtende rr manually download, inst NetExtender	NetExtender Client r Client all and launch NetExtender Cl Help >>	ient Since NPAPI has been forbidde Virtual Assist	n by chrome and
Request Assistance	۲	Virtual Access	
	to the Dell Soni tual Office provides secure e network resources via SS red bookmark or create yo resources. er to create an SSLVPN tun lownload Windows Mobile M lownload Linux NetExtende er manually download, inst NetExtender Request Assistance	to the Dell SonicWALL Virtual Of tual Office provides secure Internet access for remote use network resources via SSLVPN technology. red bookmark or create your own to gain secure Interner resources. er to create an SSLVPN tunnel to your corporate network lownload Windows Mobile NetExtender Client lownload Linux NetExtender Client er manually download, install and launch NetExtender Cli NetExtender Help>> Request Assistance	transmission transmission

a questo punto cliccate su (NetExtender) per scaricare il software

8)pening NetExtender.tgz
You	nave chosen to open:
1 - O 10 10	NetExtender.tgz
	which is: Archivio tar (compresso con gzip) (1,7 MB) from: https://172.16.16.1:4433
Wou	ld you like to save this file?
	Cancel Save File

una volta completato il download aprite il file NetExtender.tgz

estrarre il contenuto del tgz esempio:

tar -xvzf NetExtender.tgz

lanciate il file ./install assicurandosi di dare il consenso al "demone pppd" se richiesto



SERVIZIO SISTEMI INFORMATIVI SEDE CENTRALE ROMA

🛛 🙁 🖻 🔹 root@sigre-v	virtual-machine: ~/Scaricati	/netExtenderClient		
root@sigre-virtual	-machine:~# cd Scaric	ati/netExtenderCl	ient/	
ca-bundle.crt	netExtender	NetExtender.jar	uninstallNetExtender	
icons	netExtender.1	nxMonitor		iref
install	NetExtender.desktop	README		h
libNetExtender.so	netExtenderGui	sslvpn		
root@sigre-virtual	-machine:~/Scaricati/	netExtenderClient	# chmode install	Ê
No command 'chmode	' found, did you mean	:		
Command 'chmod' f	rom package 'coreutil	s' (main)		
chmode: command no	t found			
root@sigre-virtual	<pre>-machine:~/Scaricati/</pre>	netExtenderClient	# ./install	

Termina	al
	😣 🔿 💿 root@sigre-virtual-machine: ~/Scaricati/netExtenderClient
0	root@sigre-virtual-machine:~/Scaricati/netExtenderClient# chmode install
	Command 'chmode' round, did you mean: Command 'chmod' from package 'coreutils' (main)
	chmode: command not found
	root@sigre-virtual-machine:~/scaricati/netExtenderclient# ./install Dell SonicWALL NetExtender 7.5.775 Installer
	Checking library dependencies
	Checking pppd Do you want non-root users to be able to run NetExtender?
	If so, I can set pppd to run as root, but this could be
	considered a security risk.
	Set pppd to run as root [y/N]? y
	mode of `/usr/sbin/pppd' retained as 4754 (rwsr-xr) mode of `/usr/sbin/pppd' channed from 4754 (rwsr-xr) to 4755 (rwsr-xr-x)
	mode of `/etc/ppp' retained as 0755 (rwxr-xr-x)
	<pre>mode of `/etc/ppp/peers' changed from 2750 (rwxr-s) to 2754 (rwxr-sr) mode of `/etc/ppp/peers/provider' changed from 0640 (rw-r) to 0644 (rw-r</pre>
2202)
	<pre>mode of `/etc/ppp/peers' changed from 2754 (rwxr-sr) to 2755 (rwxr-sr-x) Copving files</pre>
U	INSTALLATION SUCCESSFUL
	To launch NetExtender, do one of the following:
2	1. Click the NetExtender icon under the Applications menu
	(look under the 'Internet' or 'Network' category)
·	or 2. Type 'netExtenderGui'
	root@sigre-virtual-machine:~/Scaricati/netExtenderClient# root@sigre-virtual-machine:~/Scaricati/netExtenderClient#
	to complete l'installazione andare sul dash home, e cecare NetExtend
una voi	ta completata i instantazione andare sul dasii nome e cecare i venzitene



SERVIZIO SISTEMI INFORMATIVI SEDE CENTRALE ROMA



cliccate sull'icona se il cliente no si avvia va insatllata una versione diversa di Java

procedere cosi:

- 1) sudo add-apt-repository "deb http://archive.canonical.com/ lucid partner"
- 2) sudo apt-get update
- 3) sudo apt-get istall default-jre

una volta completata l'instalazione di Java rilanciare da dash home e cecare NetExtender, a questo punto si avvierà l'interfaccia dove dovrete inserire alcune info

Server ,Username, password e dominio



SERVIZIO SISTEMI INFORMATIVI SEDE CENTRALE ROMA

8 Net	Extender r Window Help	
Dell Son	nicWALL NetExtender	
	Server: Username: Password: Domain: Connect	n IS 1
	Save name and password (if allowed)	t
2 > 0		© 2015 Dell 🕄

server : <u>193.206.131.110</u>

user:

Password:

Dominio: cnrinmrm.local



SERVIZIO SISTEMI INFORMATIVI SEDE CENTRALE ROMA

😕 🔵 Net letExtende	Extender r <u>W</u> indow <u>H</u> elp	
Dell Sor	nicWALL NetExtender	
	Server: 172.16.16.1:4433 Username: Test Password: Domain: insean.tt Connect Save name and password (if allowed)	
2 - 0		© 2015 Dell

Cliccare su connetti, accettare il certificate.